


# How to set up email account on iPhone (SSL)


Document by Dylan

Date: 8/2/2018


1. Go to Settings on your iPhone



2. Tap Accounts & Passwords




3. select Add Account



4. select Other, then click add a mail account.



Click the Add Mail Account to create a new email account



5. Fill in all the required fields, once finish fill in all the required field click next

Name	Example
Email	example@yourdomain.com
Password	●●●●●●
Description	Yourdomain

Name: Your Own Name

Email: [example@yourdomain.com.sg](mailto:example@yourdomain.com.sg) (Your own email address)

Password: Your own email password

Description: Your domain (Use your own Description because different account domain different Description)

6. Select IMAP, fill in all the required fields for the Incoming and Outcoming mail server then tap Next to verify the email account.

<input checked="" type="radio"/> IMAP		<input type="radio"/> POP
Name	Example	
Email	example@yourdomain.com	
Description	Yourdomain	
INCOMING MAIL SERVER		
Host Name	mail.yourdomain.com	
Username	example@yourdomain.com	
Password	●●●●●●	
OUTGOING MAIL SERVER		
Host Name	mail.yourdomain.com	
Username	example@yourdomain.com	
Password	●●●●●●	

Host Name: your own domain hostname (example: mail.yahoo.com)

Username: [example@yourdomain.com](mailto:example@yourdomain.com) (Refer to your own email account)

Password: your email password

**\*Entered all the details using your own email address.**


7. Verify the email account. After the verification process makes sure to enable the Mail, then tap Save.



### 8. Steps to configure SSL Setup

Go to Setting > Accounts & Password > click the Description (your own email domain account) > click Account > On the Outgoing Mail Server(SMTP), click it > click the mail.yourdomain.com.sg > enable the Use SSL > for the Server Port change to 465(587 is without a SSL). Wait for it to verify.

Outgoing Mail Server:




After done with the verification, go back to the Account and select Advanced. In the Advance setting, there is an Incoming Setting > enable Use SSL > Server Port change to 993. After done with all the step, you are finished.

Incoming Mail Server:

INCOMING SETTINGS

---

Use SSL 

---

Authentication Password >

---

IMAP Path Prefix /

---

Server Port 993